

Before You Install the Client—*Read This First!*

Types of Installation

Before installing UD/MIPS client on your PC, determine the following:

- If UD/MIPS has never been installed on your PC before, proceed to **Section 1.0—Complete Installation**.
- If a previous version UD/MIPS is currently on your PC, proceed to **Section 2.0—Overwrite Installation**.
- If you want to connect to the server from your local PC in order to use less memory and hard drive space on your workstation, proceed to **Section 3.0—Connect to Server Installation**.
- If you want to uninstall a previous version of UD/MIPS, proceed to **Section 4.0—Uninstalling the Client**.

Before you begin these procedures...

- Log in to the Client with Administrator-level access.

Before you install UD/MIPS on your PC (the Client), you must prepare your PC as follows:

- Remove extraneous programs and files
- Ensure the Server meets the minimum requirements identified in the **Hardware Requirements** topic.

Standalone (Minimum)

Processor:	Pentium II 400MHz
RAM:	128MB
CDROM:	8x
Hard Disk:	5GB
Backup:	N/A
Mouse:	Recommended
Video Card:	800 X 600, 256 colors
Operating System:	Windows NT 4.0/2000

- De-fragment hard disks
- Ensure your PC meets the minimum requirements identified in the **Hardware Requirements** topic
- Back up important files.

Note: Export the following files: ELSIGs, DFR, Sections, DFR notes, Tickler sections, Impromptu IMR files, user fields, user field labels, and all intelligent forms. If you have information in the datalink directory, back it up in a safe location, or it will be lost after installation. If you have DBUM installed on your PC, export the DBUM user list, as well.

This software can be copied to a network-accessible drive. The directory selected for the installation should follow the MS-DOS (8.3) file-naming format. If the MS-DOS format is not used, the installation may fail in some network operating environments.

Note: Throughout the install and uninstall topics, the lowercase "x" represents the letter that your machine uses to denote its local hard disk, CD-ROM drive, or network drive. For example, if Windows is located on the machine's "C:" drive, "<drive:>\windows" equals "C:\windows".

- Ensure the appropriate printer driver is installed and configured
- Close all open applications
- Disable any anti-virus programs you have installed on your PC.

Section 1.0—Complete Installation

If UD/MIPS has never been installed on the PC, you may perform a **Complete** or a **Remote** installation. The installation process varies in time depending on computer speeds.

Before you begin these procedures...

1. See the **Before You Install the Client** topic.
2. Log in to the PC with Administrator-level access.

Of particular importance are the following points:


- Disable any anti-virus programs you have installed on your PC.
- Back up important files. The **Before You Install the Client** topic contains a list of recommended files.
- If you currently have UD/MIPS SR2001.2 installed on your PC, follow the procedures in the **Uninstalling the Client** topic.




Caution: If you have information in the datalink directory, back it up in a safe location, or it will be lost after installation.

To Install the Client


1. Start the **SETUP.EXE** program on your PC from either the CD drive or the network drive, e.g., "<drive:>\directory\setup.exe". The **InstallShield Wizard, Welcome** window opens.




2. Choose **Next**. The **Software License Agreement** window opens.




3. Choose **Yes**. The **Install Shield Wizard, Setup Type** for **Options** window opens.



4. Select all of the options. All the components are necessary for UD/MIPS to function properly.
Note: You can switch between the local and remote databases after you have installed the Client. For more information, see the **Switching Database Connections** topic.
5. Choose **Next**.
6. If Oracle has been installed on this PC before, a message informs you that there are files that must be removed before you can proceed and prompts you to reboot.



7. Choose **Yes**. A message warns you the setup process will reboot your machine.




8. Choose **OK**. The PC reboots, and you need to begin again at step one of this section.
9. After the setup status is complete, the **InstallShield Wizard, Enter Text** window opens.



10. In the **Select a target drive for your oracle software** box, type your hard drive name.
11. Choose **Next**.


Note: If Oracle has already been installed on this machine, the **InstallShield Wizard, Enter Text** window will not display.

12. The **InstallShield Wizard, Choose Destination Location** window opens. If you want to install UD/MIPS in another folder, choose **Browse** to select the new destination.




Note: The default destination folder is C:\UDMIPS. It is recommend that you do not change this directory. However, if UD/MIPS was previously installed use the **Browse** option to select the drive or directory that UD/MIPS was installed to.


13. Choose **Next**. The **InstallShield Wizard, Setup Status** window opens.




14. A message informs you that Oracle software is being installed. The installation process begins.




15. A message informs you that Oracle Database Configuration Assistant is creating your database. This window appears only if you choose a local database.




16. After the database restarts, an **Oracle SQL*Plus** window opens. This window appears only if you choose a local database.




17. Several **Oracle SQL*Plus** windows display various scripts as the database and tables are created.
18. A message informs you that Setup has launched Impromptu user installation.



19. If Adobe Acrobat Reader 4 is not currently installed on your machine, the **Install Adobe Acrobat Reader 4.05c** window opens.




20. Do one of the following:
- If you want to install Acrobat on your PC, choose **Yes**.
 - If you do not want to install Acrobat on your PC, choose **No**.
21. If you choose **Yes**. The **Acrobat Reader 4.05c** window opens.




Note: If a previous version of Adobe Acrobat Reader was installed onto your PC, select **install AR4 and remove the previous version**.

22. Choose **Next**. A message informs you that Acrobat Reader is installing.



23. When installation is complete, the **InstallShield Wizard, Maintenance Complete** window opens.



24. Choose **Finish**. The **InstallShield Wizard** window closes.

If the Database Is on the Client

Before you can use UD/MIPS, you must initialize the local database. Don't forget to import all the files you exported from the previous version.

To Connect to the Server

If you want to connect to the server database, refer to the **Setting Up the Server Connection** topic. Login with **Oracle Login** and then with the UD/MIPS ELSIG. Before you can use UD/MIPS, if you did not have the install make the server connection, or if there was an error, then you will have to establish the connection between the Client (your PC) and the Server.

The Next Step

- Do one of the following:
 - After following these procedures, proceed to the **Setting Up the Server Connection** topic.

- If you experienced a problem with these procedures, proceed to the **Uninstalling the Client** topic.

Section 2.0—Overwrite Installation

If there is a previous version of UD/MIPS on your PC, you must perform an **Overwrite** installation. The installation process varies in time depending on computer speeds.

Before you begin these procedures...

1. See the **Before You Install the Client** topic.
2. Log in to the PC with Administrator-level access.

Of particular importance are the following points:


- Disable any anti-virus programs you have installed on your PC.
- Back up important files. The **Before You Install the Client** topic contains a list of recommended files.




Caution: If you have information in the datalink directory, back it up in a safe location, or it will be lost after installation.

To Install the Client


1. Start the **SETUP.EXE** program on your PC from either the CD drive or the network drive, e.g., "<drive:>\directory\setup.exe". The **InstallShield Wizard, Welcome** window opens.



2. Choose **Next**. The **Software License Agreement** window opens.




3. Choose **Yes**. The **Install Shield Wizard, Setup Type** for **Options** window opens.



4. Select **Re-Initialize database to version 2002.1.000** and **UD/MIPS Application**. These options allow you to install only the portions you need to overwrite the previous version of UD/MIPS.

Note: You can switch between the local and remote databases after you have installed the Client. For more information, see the **Switching Database Connections** topic.


5. Choose **Next**.




6. The **InstallShield Wizard, Choose Destination Location** window opens. If you want to install UD/MIPS in another folder, choose **Browse** to select the new destination.

Note: The default destination folder is C:\UDMIPS. It is recommend that you do not change this directory.

7. Choose **Next**.
8. If Oracle has been installed on this PC before, a message informs you that there are files that must be removed before you can proceed and prompts you to reboot.




9. Choose **Yes**. A message warns you the setup process will reboot your machine.




10. Choose **OK**. The PC reboots, and you need to begin again at step one of this section.

11. Choose **Next**. The **InstallShield Wizard, Setup Status** window opens.




12. An **Oracle SQL*Plus** window opens.



13. Several **Oracle SQL*Plus** windows display various scripts as the database and tables are created.


14. If Adobe Acrobat Reader 4 is not currently installed on your machine, the **Install Adobe Acrobat Reader 4.05c** window opens.



15. Do one of the following:


- If you want to install Acrobat on your PC, choose **Yes**.
- If you do not want to install Acrobat on your PC, choose **No**.

16. If you choose **Yes**. The **Acrobat Reader 4.05c** window opens.





Note: If a previous version of Adobe Acrobat Reader was installed onto your PC, select **install AR4 and remove the previous version**.

17. Choose **Next**. A message informs you that Acrobat Reader is installing.



18. When installation is complete, the **InstallShield Wizard, Maintenance Complete** window opens.



Note: Depending on the setting in registry during this process, one of these windows will open.

19. Choose **Finish**. The **InstallShield Wizard** window closes.

If the Database Is on the Client

Before you can use UD/MIPS, you must initialize the local database. Don't forget to import all the files you exported from the previous version.

To Connect to the Server

If you want to connect to the server database, refer to the **Setting Up the Server Connection** topic. Login with **Oracle Login** and then with the UD/MIPS ELSIG. Before you can use UD/MIPS, if you did not have the install make the server connection, or if there was an error, then you will have to establish the connection between the Client (your PC) and the Server.

The Next Step

- Do one of the following:
 - After following these procedures, proceed to the **Setting Up the Server Connection** topic.
 - If you experienced a problem with these procedures, proceed to the **Uninstalling the Client** topic.

Section 3—Connect to Server Installation

If you want your PC to connect to the server in order to save on your machine's memory and hard drive space, perform a **Connect to Server** installation. This topic gives you step-by-step instructions on how to install UD/MIPS on your PC (the Client). The installation process varies in time depending on computer speeds.

Before you begin these procedures...

1. See the **Before You Install the Client** topic.
2. Log in to the PC with Administrator-level access.

Of particular importance are the following points:


- Disable any anti-virus programs you have installed on your PC.
- Back up important files. The **Before You Install the Client** topic contains a list of recommended files.
- If you currently have UD/MIPS SR2001.2 installed on your PC, follow the procedures in the **Uninstalling the Client** topic.




Caution: If you have information in the datalink directory, back it up in a safe location, or it will be lost after installation.

To Install the Client


1. Start the **SETUP.EXE** program on your PC from either the CD drive or the network drive, e.g., "<drive:>\directory\setup.exe". The **InstallShield Wizard, Welcome** window opens.




2. Choose **Next**. The **Software License Agreement** window opens.




3. Choose **Yes**. The **Install Shield Wizard, Setup Type** for **Options** window opens.




4. Select **Oracle Client Software**, **Impromptu User 6.0 Application**, and **UD/MIPS Application**. These options allow you to install only the portions you need to overwrite the previous version of UD/MIPS.
5. Choose **Next**.
6. If UD/MIPS has been installed on this PC before, a message informs you that there are files that must be removed before you can proceed and prompts you to reboot.



7. Choose **Yes**. A message warns you the setup process will reboot your machine.




8. Choose **OK**. The PC reboots, and you need to begin again at step one of this section.
9. If you chose to install Oracle without loading a local Oracle database, a message prompts you to confirm that you want Setup to make a TNS entry.




10. Choose **Yes**.

11. If you choose to make a TNS Entry, the **TNS Names Entry Parameters** window opens. In the **Address** box, type the physical IP address or the domain name if name resolution is available. You cannot leave this box blank.



12. If the TNS Alias entry already exists in your TNSNAMES file, a message prompts you to confirm if you want to overwrite the entry.


Note: Depending on the setting in registry during this process, this window may or may not open.



13. Do one of the following:


- If you want to overwrite the entry, choose **Yes**. The **InstallShield Wizard, Choose Destination Location** window opens.
- If you do not want to overwrite the entry, choose **No**. You return to the **TNS Names Entry Parameters** window.

14. The **InstallShield Wizard, Choose Destination Location** window opens. If you want to install UD/MIPS in another folder, choose **Browse** to select the new destination.




Note: The default destination folder is C:\UDMIPS. It is recommend that you do not change this directory. However, if UD/MIPS was previously installed use the **Browse** option to select the drive or directory that UD/MIPS was installed to.

15. Choose **Next**. The **InstallShield Wizard, Setup Status** window opens.




16. If Adobe Acrobat Reader 4 is not currently installed on your machine, the **Install Adobe Acrobat Reader 4.05c** window opens.



17. Do one of the following:


- If you want to install Acrobat on your PC, choose **Yes**.
- If you do not want to install Acrobat on your PC, choose **No**.

18. If you choose **Yes**. The **Acrobat Reader 4.05c** window opens.




Note: If a previous version of Adobe Acrobat Reader was installed onto your PC, select **install AR4 and remove the previous version**.

19. Choose **Next**. A message informs you that Acrobat Reader is installing.



20. When installation is complete, the **InstallShield Wizard, Maintenance Complete** window opens.



21. Choose **Finish**. The **InstallShield Wizard** window closes.

The Next Step

- Do one of the following:
 - After following these procedures, proceed to the **Setting Up the Server Connection** topic.
 - If you experienced a problem with these procedures, proceed to the **Uninstalling the Client** topic.

Section 4.0—Uninstalling the Client

Uninstalling the Client involves many separate operations. You must uninstall the Database User Management (DBUM) System software (if installed), uninstall UD/MIPS, stop specific Oracle-related services, uninstall the current Oracle software, and shutdown and restart the PC.


Important: These procedures assume that no other software has been installed on your machine that uses Oracle services, e.g., web services products, FTP products, etc. These other Oracle-related products must be removed prior to performing these procedures. Contact your Server Administrator for assistance.

Before you begin these procedures...

1. See the **About Install/Uninstall** topic.
2. See the **Before You Install the Client** topic.
3. Follow the DBUM System uninstall instructions in the DBUM Help topics.
4. Log in to the PC with Administrator-level access.

To Uninstall UD/MIPS


These instructions apply to all current releases, Local and Remote installations.



1. On the Desktop Task Bar, choose **Start**, select **Settings**, then choose **Control Panel**. The **Control Panel** window opens.




2. On the **Control Panel**, choose **Add/Remove Programs**. The **Add/Remove Programs Properties** window opens.




- On the **Install/Uninstall** tab, in the list, select **Unit Diary - Marine Integrated Personnel System**, then choose **Add/Remove**. The **InstallShield Wizard, Setup** window opens briefly. The progress indicator shows the status of the setup process.




- When the setup process completes, a message prompts you to confirm the delete process.




5. Choose **OK**. Choose **OK**. The **Removed Shared File** window or **Shared File Detected** window may open.
6. You may encounter one of the following windows:



- If the **Shared File Detected** window opens, select the **Don't display this message again** check box and choose **Yes**.




- If the **Removed Shared File** window opens, choose **Yes To All**. A message prompts you to confirm the delete process. Choose **OK**. A message prompts you to confirm the delete process.
7. When the uninstall process completes, the **InstallShield Wizard, Maintenance Complete** window opens.




8. Continue with the **To Uninstall Impromptu** section in the topic.

To Uninstall Impromptu


1. Begin on the **Add/Remove Programs Properties** window.




2. Select **Cognos BI**, then choose **Add/Remove**. The **Uninstall Wizard** window opens.




3. Choose **Next**. The **Uninstalling the Software** window opens.




4. Select **Select All** and choose **Next**. The **Uninstall** window opens.



5. Choose **Yes**. The **Uninstall Progress** window indicates how the uninstall is progressing.




6. The **Uninstallation Completed** window opens.




7. Select **No, I will restart my computer later** and choose **Finish**. You return to the **Add/Remove Programs Properties** window.
8. Choose **Cancel**. You return to the **Control Panel** window.
9. Close the **Control Panel** window and proceed to the **To Uninstall Oracle** section later in this topic.

To Uninstall Oracle




1. On the **Desktop Task Bar**, choose **Start**, select **Programs**, select **Oracle Installation Products**, and then choose **Universal Installer**. The **Oracle Universal Installer** window opens.




2. Choose **Deinstall Products**. The **Inventory** window opens.


Note: The list of software on the window may not be the same as in this graphic.





3. Expand the **Independent Products** item.
4. Expand the **OraHome81** item.
5. Check all items for the **Independent Products** and **OraHome81** dependent components.



6. Choose **Remove**. The **Confirmation** window opens. It prompts you to confirm the items you have selected to uninstall.




7. Choose **Yes**. The **Remove** window opens.




8. When the uninstall process completes, you return the **Inventory** window. The **Independent Products** and **OraHome81** items should be gone from the list.

Note: The list of software on the window may not be the same as in this graphic.

9. Choose **Close**. You return to the **Oracle Universal Installer** window.



10. Choose **Exit**. The **Exit** window opens.



11. Choose **Yes**. The **Exit** window closes.

To Complete the Uninstall

- **Shutdown** and **Restart** your machine.

The Next Step

- If you want to reinstall the Client, proceed to the **Installing the Client** topic.